


PT Activity 3.6.1: Packet Tracer Skills Integration Challenge

Topology Diagram



Addressing Table

Device	Interface	IP Address	Subnet Mask	Default Gateway
S1	VLAN 99	172.17.99.31	255.255.255.0	172.17.99.1
S2	VLAN 99	172.17.99.32	255.255.255.0	172.17.99.1
S3	VLAN 99	172.17.99.33	255.255.255.0	172.17.99.1
PC1	NIC	172.17.10.21	255.255.255.0	172.17.10.1
PC2	NIC	172.17.20.22	255.255.255.0	172.17.20.1
PC3	NIC	172.17.30.23	255.255.255.0	172.17.30.1
PC4	NIC	172.17.10.24	255.255.255.0	172.17.10.1
PC5	NIC	172.17.20.25	255.255.255.0	172.17.20.1
PC6	NIC	172.17.30.26	255.255.255.0	172.17.30.1

Learning Objectives

- Add and connect switches.
- Add and connect PCs.
- Verify basic device configuration and connectivity.
- Configure and verify port security.
- Configure VLANs on the switches.
- Configure trunks on the switches.
- Verify end-to-end connectivity.

Introduction

In this activity, you will connect and completely configure the Chapter 3 topology, including adding and connecting devices, and configuring security and VLANs.

Task 1: Add and Connect the Switches

Step 1. Add the S2 switch.

S2 must be a 2960 series switch. Change the **Display Name** and **Hostname** to S2. Names are case-sensitive.

Step 2. Connect S2 to S1.

Connect S2 Fa0/1 to S1 Fa0/1.

Step 3. Check results.

Your completion percentage should be 5%. If not, click **Check Results** to see which required components are not yet completed.

Step 4. Add the S3 switch.

S3 must be a 2960 series switch. Change the **Display Name** and **Hostname** to S3. Names are case-sensitive.

Step 4. Connect S3 to S1.

Connect S3 Fa0/3 to S1 Fa0/3.

Step 5. Check results.

Your completion percentage should be 9%. If not, click **Check Results** to see which required components are not yet completed.

Task 2: Add and Connect the PCs

Step 1. Add PC1, PC2, PC3, PC4, PC5, and PC6.

- Add the six PCs according to the chapter topology.
- If necessary, change the **Display Name** to match the names in the addressing table. Display names are case-sensitive.

Step 2. Connect PC1, PC2, and PC3 to S2.

- Connect PC1 to Fa0/11 on S2
- Connect PC2 to Fa0/18 on S2
- Connect PC3 to Fa0/6 on S2

Step 3. Connect PC4, PC5, and PC6 to S3.

- Connect PC4 to Fa0/11 on S3
- Connect PC5 to Fa0/18 on S3
- Connect PC6 to Fa0/6 on S3

Step 4. Check results.

Your completion percentage should be 32%. If not, click **Check Results** to see which required components are not yet completed.

Task 3: Configure Devices and Verify Connectivity

Step 1. Configure switches with basic commands.

Configure each switch with the following basic settings.

- Hostname on S1
- Enable secret password
- Line configurations
- Service encryption

Step 2. Configure the management VLAN interface on S1, S2, and S3.

Configure VLAN 99 as the management VLAN interface on S1, S2, and S3. This interface is not active until after trunking is configured later in the activity. However, activate the interface at this time with the appropriate command.

Step 3. Configure PC IP addressing.

Configure the PCs with IP addressing according to the addressing table.

Step 4. Verify that PCs on the same subnet can ping each other.

Switch to **Simulation** mode and use the **Add Simple PDU tool to create** pings between PCs on the same VLAN. Verify that the following PCs can ping each other:

- PC1 to PC4
- PC2 to PC5
- PC3 to PC6

Step 5. From Simulation mode, observe the broadcast traffic.

- Clear the learned MAC addresses so that the switches must broadcast ping packets.
- From **Simulation** mode, observe the broadcast traffic that propagates throughout the LAN until the switches learn the ports of each PC.

Step 6. Check results.

Your completion percentage should be 53%. If not, click **Check Results** to see which required components are not yet completed.

Task 4: Configure and Verify Port Security

Step 1. Configure access links with port security.

Normally, you configure port security on all access ports or shut down the port if it is not in use. Return to **Realtime** mode and use the following policy to establish port security just on the ports used by the PCs.

- Set the port to access mode.
- Enable port security.
- Allow only one MAC address.
- Configure the first learned MAC address to “stick” to the configuration.

- Set the port to shut down if there is a security violation.

Force the switches to learn the MAC addresses by sending pings across all three switches

Note: Only enabling port security is graded by Packet Tracer. However, all the port security tasks listed above are required to complete this activity.

Step 2. Verify port security is active for the interfaces attached to PCs.

What command would you use to verify that port security is active on an interface?

```
Port Security           : Enabled
Port Status            : Secure-up
Violation Mode         : Shutdown
Aging Time             : 0 mins
Aging Type             : Absolute
SecureStatic Address Aging : Disabled
Maximum MAC Addresses  : 1
Total MAC Addresses    : 1
Configured MAC Addresses : 1
Sticky MAC Addresses   : 0
Last Source Address:Vlan : 0050.0F00.6668:1
Security Violation Count : 0
```

Note: The **Last Source Address:Vlan** information should show a MAC address. Your MAC address may be different than the one shown here. If the MAC address in this field is 0000.0000.0000, send traffic to the port by pinging across the switch to the other PC on the same subnet.

Step 3. Test port security.

- Connect PC2 to the port of PC3, and connect PC3 to the port of PC2.
- Send pings between PCs on the same subnet.
- The ports for PC2 and PC3 should shut down.

Step 4. Verify that ports are err-disabled and that a security violation has been logged.

What command shows the following output?

```
FastEthernet0/6 is down, line protocol is down (err-disabled)
  Hardware is Lance, address is 000a.41e8.c906 (bia 000a.41e8.c906)
<output omitted>
```

What command shows the following output?

```
Port Security           : Enabled
Port Status            : Secure-shutdown
Violation Mode         : Shutdown
Aging Time             : 0 mins
Aging Type             : Absolute
SecureStatic Address Aging : Disabled
Maximum MAC Addresses  : 1
Total MAC Addresses    : 1
Configured MAC Addresses : 1
Sticky MAC Addresses   : 0
```

```
Last Source Address:Vlan    : 0050.0F00.6668:1
Security Violation Count    : 1
```

Step 5. Reconnect PCs to the correct port and clear port security violations.

- Connect PC2 and PC3 back to the correct port.
- Clear the port security violation.
- Verify that PC2 and PC3 can send pings across S2.

Step 6. Check results.

Your completion percentage should be 75%. If not, click **Check Results** to see which required components are not yet completed.

Task 5: Configure VLANs on the Switches

Step 1. Create and name the VLANs.

Create and name the following VLANs on the switches S1, S2, and S3:

- VLAN 10, name = **Faculty/Staff**
- VLAN 20, name = **Students**
- VLAN 30, name = **Guest(Default)**
- VLAN 99, name = **Management&Native**

Step 2. Assign access ports to the VLANs.

Assign the following PC access ports to the VLANs:

- VLAN 10: PC1 and PC4
- VLAN 20: PC2 and PC5
- VLAN 30: PC3 and PC6

Step 3. Verify VLAN implementation.

What command verifies the VLAN configuration, including the port assignments?

```

VLAN Name                Status    Ports
-----
1    default                active    Fa0/1, Fa0/2, Fa0/3, Fa0/4
                                           Fa0/5, Fa0/7, Fa0/8, Fa0/9
                                           Fa0/10, Fa0/12, Fa0/13, Fa0/14
                                           Fa0/15, Fa0/16, Fa0/17, Fa0/19
                                           Fa0/20, Fa0/21, Fa0/22, Fa0/23
                                           Fa0/24, Gig1/1, Gig1/2
10   Faculty/Staff           active    Fa0/11
20   Students                active    Fa0/18
30   Guest(Default)         active    Fa0/6
99   Management&Native       active
<output omitted>

```

Step 4. Check results.

Your completion percentage should be 92%. If not, click **Check Results** to see which required components are not yet completed.

Task 6: Configure Trunks on the Switches

Step 1. Configure trunking on the appropriate interfaces.

- Configure trunking on the appropriate interfaces on switch S1.
- Verify that switches S2 and S3 are now in trunking mode.
- Manually configure the appropriate interfaces on S2 and S3 for trunking.
- Configure VLAN 99 as the native VLAN for all trunks.

Step 2. Test connectivity

After the switch trunk ports transition to the forwarding state (green link lights), you should be able to successfully ping between PCs on the same VLAN.

Step 3. Check results.

Your completion percentage should be 100%. If not, click **Check Results** to see which required components are not yet completed.